




สำนักคอมพิวเตอร์  
Computer Center

# VIRTUAL PRIVATE NETWORK SERVICE (VPN)

Windows 11

## Virtual Private Network Service




# Manual setup L2TP over IPsec for Windows 11


- [Procedure to set up L2TP/IPsec](#)
  - [Procedure to login into L2TP/IPsec](#)
  - [Procedure to disconnect from L2TP/IPsec](#)
  - [Procedure to uninstall L2TP/IPsec](#)
- 

## ➤ Procedure to set up L2TP/IPsec


1. Open (Right click) **Network** on Taskbar
2. Go to **Network & Internet settings**



3. Go to **VPN**



4. Click **Add VPN**



5. Set the following settings:

5.1 VPN provider: **Windows (built-in)**

5.2 Connection name: **KMUTTVPN**

5.3 Server name or address: **vpn.kmutt.ac.th**

5.4 VPN type: **L2TP/IPsec with pre-shared key**

5.5 Pre-shared key: **kmutt.ac.th**

5.6 Type of sign-in info: **username and password**

5.7 Username (optional): **username.sur** (Ex. username.sur or 6xxxxxxxxxx)

5.8 Password (optional): **\*\*\*\*\*** (same as email password)

5.9 Click **Remember my sign-in info**

5.10 Click **Save**


## Add a VPN connection

5.1 VPN provider  
Windows (built-in) ▾

5.2 Connection name  
KMUTTVPN

5.3 Server name or address  
vpn.kmutt.ac.th

5.4 VPN type  
L2TP/IPsec with pre-shared key ▾

5.5 Pre-shared key  
kmutt.ac.th 

5.6 Type of sign-in info  
Username and password ▾

5.7 Username (optional)  
username.sur

5.8 Password (optional)  
●●●●●●●●

Remember my sign-in info

5.10

6. Go to **KMUTTVPN**

7. Go to **Advanced options**

Network & internet > VPN

VPN connections

6  KMUTTVPN  
Not connected  ^

7

8. Go to **Edit** at **More VPN properties**




9. Go to **Security**

10. Set the following settings:

10.1 Click **(•) Allow these protocols**


10.2 Click **[/]** **Challenge Handshake Authentication Protocol (CHAP)** and **Microsoft CHAP Version 2 (MS-CHAP v2)**

11. Click **OK**




➤ Procedure to login into L2TP/IPsec

1. Open **Network** on Taskbar
2. Go to **VPN**




3. Choose **KMUTTVPN** and **Connect**




➤ Procedure to disconnect from L2TP/IPsec

1. Open **Network** on Taskbar
2. Go to **VPN**




3. Click **Disconnect**




➤ Procedure to uninstall L2TP/IPsec

1. Open (Right click) **Network** on Taskbar
2. Go to **Network & Internet settings**



3. Go to **VPN**



4. Choose **KMUTTVPN** profile, must be disconnected
5. Click **Remove**

