


## Virtual Private Network Service




## Manual for Setting Up L2TP over IPsec on Windows 8

- Steps for Configuring L2TP/IPsec
  - Steps for Logging into the System to Use L2TP/IPsec
  - Steps for Disconnecting from L2TP/IPsec
  - Steps for Uninstalling L2TP/IPsec
- 


### ➤ Steps for Configuring L2TP/IPsec

1. Click on **Network** from the Taskbar

2. Select **Open Network and Sharing Center**




3. When the Network and Sharing Center window appears, select **Set up a new connection or network**.




4. When the Set up a new connection or network window appears.

4.1 Select **Connect to a workplace**

4.2 Click **Next**



5. When the Connect to a Workplace window appears, select **Use my Internet connection (VPN)**.




6. When the settings window appears, configure as follows.


6.1 Internet address: **vpn.kmutt.ac.th**

Destination name: **KMUTTVPN**

6.2 Click **Create**




7. In the Network and Sharing Center window, select **Change adapter settings**.



8. When the Network Connections window appears.

8.1 Right-click on **KMUTTVPN**

8.2 Select **Properties**



9. In the KMUTTVPN Properties window, select the **Security** tab and configure the settings as follows:

9.1 Select **Security**

9.2 Type of VPN: **Layer 2 Tunneling with IPsec (L2TP/IPsec)**

9.3 Select **Advanced settings**

The Advanced Properties window appears.

9.3.1 Select **Use preshared key for authentication**

Key: **kmutt.ac.th**


9.3.2 Click **OK**

9.4 Return to the KMUTTVPN Properties window.

9.4.1 Select **(•) Allow these protocols**

9.4.2 Select **[/] Challenge Handshake Authentication Protocol (CHAP) only**


9.5 Click **OK**



## ➤ Steps for Logging into the System to Use L2TP/IPsec

1. Click on **Network** from the **Taskbar**

2. Select **KMUTTVPN** and Click **Connect**



4. Please enter the Username and Password to connect to the VPN.

4.1 Username (optional) : **username.sur** (User name, such as username.sur or 6xxxxxxxxxx, must be clearly specified)

Password (optional) : **\*\*\*\*\*** (User password must be entered correctly)


4.2 Click **OK**





### ➤ Steps for Disconnecting from L2TP/IPsec


1. Click on **Network** from the Taskbar.
2. Select **KMUTTVPN** that is currently Connected.
3. Click **Disconnect**




## ➤ Steps for Uninstalling L2TP/IPsec

1. Click on Network from the Taskbar

2. Select Open Network and Sharing Center



3. When the Network and Sharing Center window appears, select **Change adapter settings** from the left-hand tab.



4. Right-click on the **KMUTTVPN** profile that you have previously created.

5. Click **Delete** to remove the settings.

